



Top-to-toe warmth

COAT					
To fit chest Garment measures	cm	46	51	(18	20 in)
	cm	48	53	(19	21 in)
Length from top of shoulders	cm	29	30	(11½	12 in)
Sleeve seam	cm	15	18	(6	7 in)
Patons Childs Play Double Knitting					
Main Shade	50 gram balls	2	2		
Contrast	50 gram ball	1	1		
Patons Fairytale Double Knitting					
Main Shade	20 gram balls	4	5		
Contrast	20 gram balls	2	3		
LEGGINGS					
Length from waist to crutch	cm	20	22	(8	8¾ in)
Inside Leg	cm	20	22	(8	8¾ in)
Patons Childs Play Double Knitting	50 gram balls	2	3		
Patons Fairytale Double Knitting	20 gram balls	5	6		
MITTS					
Patons Childs Play Double Knitting					
Main Shade	50 gram ball	1	1		
Oddment of Contrast					
Patons Fairytale Double Knitting					
Main Shade/Contrast	20 gram ball	1/1	1/1		
HAT					
		up to 9 months		9–18 months	
Patons Childs Play Double Knitting					
Main Shade/Contrast	50 gram ball		1/1		1/1
Patons Fairytale Double Knitting					
Main Shade/Contrast	20 gram ball		1/1		1/1

Patons Childs Play combines high quality botany wool with special superfine acrylic to produce a yarn which is beautifully soft and gentle, but machine-washable and shrink-resistant. Childs Play is available in clear modern colours as well as pastels and white.

Patons Fairytale is soft yet machine-washable acrylic/nylon, available in white, baby pastels and pretty prints.

Pair each Nos 3¼ mm, 3¾ mm and 4 mm Milward needles. Needle sizes quoted are Metric: equivalent UK sizes are No 10 for 3¼ mm, No 9 for 3¾ mm and No 8 for 4 mm.

3 buttons for Coat. Length of elastic for Leggings. Length of ribbon for Mitts.

Tension

On No 4 mm needles, 22 sts and 30 rows to 10 cm (stocking stitch).

Caution

It is essential to work to the stated tension, and Patons and Baldwins Limited cannot accept responsibility for the finished product if any yarn other than the recommended Patons yarns is used.

Abbreviations

K=knit; P=purl; st=stitch; yfwd=yarn forward;
tog=together; tbl=through back of loops.

inc=increase by working into front and back of stitch;
dec=decrease by working 2 stitches together.

beg=beginning; alt=alternate; rep=repeat; patt=pattern;
cm=centimetres; in=inches; mm=millimetres; MS=Main
Shade; C=Contrast.

M1=make 1 stitch by picking up horizontal loop lying before
next stitch and working into back of it.

Note

Carry colour not in use loosely up side of work.

STRIPE PATT

1st row—(Right side), in MS, K. **2nd row**—In MS, P.

3rd and 4th rows—In C, K. **5th and 7th rows**—In MS, K.

6th and 8th rows—In MS, P. **9th and 10th rows**—In C, K.

These 10 rows form stripe patt.

Coat

BACK

With No 3¼ mm needles and C, cast on 70 [80] sts and work 5 rows garter stitch (every row K, **noting** that 1st row is **wrong** side).

Change to No 4 mm needles and starting with a K row, work 2 rows in stocking stitch.

Join in MS and work 10 rows in stripe patt. Break C.

Continue in MS and work in stocking stitch until Back measures 17 cm, ending with a P row.

Next row—(K2, K2tog) 4 times, (K1, K2tog) 12 [17] times, (K2, K2tog) 4 [3] times, K2 [1] (50 [56] sts).

Work straight until Back measures 18 cm, ending with a P row.

Shape raglans by casting off 2 sts at beg of next 2 rows.

Dec 1 st at each end of next and following 4th row. Work 3 [1] rows.

Now dec 1 st at each end of next and every alt row until 18 [20] sts remain, ending with a P row. Leave remaining sts on a length of yarn.

LEFT FRONT

With No 3¼ mm needles and C, cast on 35 [40] sts and work 5 rows garter stitch.

Change to No 4 mm needles and starting with a K row, work 2 rows in stocking stitch.

Join in MS and work 10 rows in stripe patt. Break C.

Continue in MS and work in stocking stitch until Front measures 17 cm, ending with a P row.

Next row—K3 [2], (K2tog, K1) 10 [12] times, K2 (25 [28] sts).

Work straight until Front matches Back to start of raglan shaping, ending with a P row.

Shape raglan by casting off 2 sts at beg of next row. Work 1 row.

Dec 1 st at beg of next and following 4th row. Work 3 [1] rows.

Now dec 1 st at beg of next and every alt row until 14 [16] sts remain, ending with a dec row.

Shape neck by casting off 3 [4] sts at beg of next row.

Now dec 1 st at raglan edge as before, **at the same time** dec 1 st at neck edge on next 4 rows (5 [6] sts).

Continue dec at raglan edge **only** until 2 sts remain, ending with a P row. **Next row**—K2tog and fasten off.

RIGHT FRONT

Work as for Left Front, reversing shapings.

SLEEVES

With No 3¼ mm needles and C, cast on 28 [30] sts and work 5 rows in garter stitch.

Change to No 4 mm needles and starting with a K row, work 2 rows in stocking stitch.

Join in MS and work 10 rows in stripe patt, **at the same time** shape sides by inc 1 st at each end of next and following 5th [6th] row (32 [34] sts). Work 4 [3] rows. Break C.

Continue in MS and stocking stitch inc 1 st at each end of every following 5th [6th] row from previous inc until there are 42 [44] sts.

Work straight until sleeve seam measures 15 [18] cm, ending with a P row.

Shape raglans by casting off 2 sts at beg of next 2 rows.

Dec 1 st at each end of next row. Work 3 rows.

Now dec 1 st at each end of next and every alt row until 8 sts remain, ending with a P row. Leave remaining sts on a length of yarn.

MAKE UP AND BORDERS

Childs Play Double Knitting—Do not press.

Fairytale Double Knitting—With wrong side of work facing, block each piece by pinning out round edges, and omitting garter stitch, press lightly following instructions on the ball band.

Both yarns: Join raglan, side and sleeve seams.

Neck Border: With right side facing, No 3¼ mm needles and C, **knit up** 12 sts up right side of neck, K8 from right sleeve dec 2 sts evenly, 18 [20] from back dec 2 sts evenly, 8 from left sleeve dec 2 sts evenly, then **knit up** 12 sts down left side of neck (52 [54] sts).

Work 6 rows in garter stitch. Cast off.

Button Border: With No 3¼ mm needles and C, cast on 5 sts and work in garter stitch until Border, when slightly stretched, fits up Right Front for Boy, Left Front for Girl to top of Neck Border, sewing in position as you go along. Cast off.

Buttonhole Border: Work as for Button Border with the addition of 3 buttonholes, first to come at start of raglan shaping, last to centre of Neck Border and remaining one space evenly between.

First mark position of buttons on Button Border with pins to ensure even spacing, then work buttonholes to correspond.

To make a buttonhole—(Right side), K2, yfwd, K2tog, K1.

Press seams on **Fairytale Double Knitting only**. Sew on buttons.

Leggings

FRONT AND BACK (alike)

With No 3¼ mm needles, cast on 62 [66] sts and work in K1, P1 rib for 2 cm.

Next row—Rib 4 [1], M1, (rib 6 [7], M1) 9 times, rib 4 [2] (72 [76] sts).

Change to No 3¼ mm needles and starting with a K row, work in stocking stitch until work measures 20 [22] cm, ending with a P row.

Next row—K32 [34], leave these sts on a length of yarn, cast off 8 sts, K to end.

Continue in stocking stitch on these 32 [34] sts for first side, shaping leg by dec 1 st at end of next and same edge on every following 3rd row until 18 [19] sts remain.

Work straight until leg measures 18 [20] cm from cast-off sts measured at centre, of work, ending with a P row. Break yarn. Leave these sts on a spare needle.

With **wrong** side facing, rejoin yarn to inside edge, P2tog, P to end.

Work to match first side, reversing shapings.

Leave remaining sts on a spare needle. Join side seams.

RIGHT FOOT

With right side facing and No 3¼ mm needles, work 2 rows in stocking stitch across 36 [38] sts of Right Leg.

Divide for foot: Next row—K to last 7 sts, turn and leave these sts on a safety-pin.

Next row—P to last 16 [17] sts, turn and leave these 16 [17] sts on a safety-pin.

**** Work 12 [14] rows stocking stitch on remaining 13 [14] sts.**

Dec 1 st at each end of next and following alt row (9 [10] sts).

Next row—P. Break yarn.**

Rejoin yarn to inside edge of 16 [17] sts and with right side facing, **knit up** 9 [10] sts along side of foot, K9 [10] on needle, **knit up** 9 [10] sts along other side of foot, then K7 from safety-pin.

Next row—K to end, then K16 [17] sts from safety-pin (50 [54] sts). K8 [10] rows.

Shape foot: 1st row—K3 [4], K2tog, K1, K2tog, K19 [20], K2tog, K2, K2tog, K17 [19]. **2nd row**—K.

3rd row—K2 [3], K2tog, K1, K2tog, K17 [18], K2tog, K2, K2tog, K16 [18]. **4th row**—K. Cast off.

LEFT FOOT

With right side facing and No 3½ mm needles, work 2 rows stocking stitch across 36 [38] sts of Left Leg.

Divide for foot: Next row—K to last 16 [17] sts, turn and leave these 16 [17] sts on a safety-pin.

Next row—P to last 7 sts, turn and leave these sts on a safety-pin. Work as for Right Foot from ** to **.

Rejoin yarn to inside edge of 7 sts and with right side facing **knit up** 9 [10] sts along side of foot, K9 [10] on needle, **knit up** 9 [10] sts along other side of foot, then K16 [17] from safety-pin.

Next row—K to end, then K7 sts from safety-pin (50 [54] sts). K8 [10] rows.

Shape foot: 1st row—K17 [19], K2tog, K2, K2tog, K19 [20], K2tog, K1, K2tog, K3 [4]. **2nd row**—K.

3rd row—K16 [18], K2tog, K2, K2tog, K17 [18], K2tog, K1, K2tog, K2 [3]. **4th row**—K. Cast off.

TO MAKE UP

Childs Play Double Knitting—Do not press.

Fairytale Double Knitting—Omitting ribbing, press as for Coat.

Both yarns: Join leg, crutch and foot seams.

Cut elastic to fit waist and join in a ring, sew inside waist ribbing using herringbone stitch over elastic to form a casing.

Press seams on **Fairytale Double Knitting only**.

Mitts

With No 3½ mm needles and C, cast on 32 [38] sts and work 3 rows garter stitch (every row K, **noting** that 1st row is **wrong** side).

Change to No 4 mm needles and starting with a K row, work 2 rows in stocking stitch.

Join in MS and work 10 rows of stripe patt. Break C.

Continue in MS and starting with a K row, work 4 rows in stocking stitch dec 2 sts evenly on last row (30 [36] sts).

Next row—* K1, yfwd, K2tog; rep from * to end. **Next row**—P.

Next row—K5 [3], (K2tog, K15 [7]) 1 [3] times, K2tog, K to end (28 [32] sts).

Starting with a P row, work in stocking stitch until Mitt measures 6 [7] cm from end of stripe patt, ending with a P row.

Shape top: 1st row—(K1, K2togtbl, K8 [10], K2tog, K1) twice. **2nd and 4th rows**—P.

3rd row—(K1, K2togtbl, K6 [8], K2tog, K1) twice. **5th row**—(K1, K2togtbl, K4 [6], K2tog, K1) twice. **6th row**—P. Cast off.

TO MAKE UP

Child's Play Double Knitting—Do not press.

Fairytale Double Knitting—Press as for Coat.

Both yarns—Join seam. Press seam on **Fairytale Double Knitting only**.

Cut two lengths of ribbon, thread through holes at wrist and tie at front.

Hat

With No 3½ mm needles and C, cast on 86 [92] sts and work 5 rows in garter stitch (every row K, **noting** that 1st row is **wrong** side).

Change to No 4 mm needles and starting with a K row, work 2 rows in stocking stitch.

Join in MS and work 10 rows in stripe patt. Break C.

Continue in MS and work in stocking stitch until Hat measures 8 [9] cm, ending with a P row dec 4 sts evenly on last row on **1st size only** (82 [92] sts).

Shape crown: 1st row—K1, (K8, K2tog) 8 [9] times, K1 (74 [83] sts).

2nd and every alt row—P.

3rd row—K1, (K7, K2tog) 8 [9] times, K1 (66 [74] sts).

5th row—K1, (K6, K2tog) 8 [9] times, K1 (58 [65] sts).

7th row—K1, (K5, K2tog) 8 [9] times, K1 (50 [56] sts).

Continue thus dec 8 [9] sts on every alt row until 18 [20] sts remain.

Next row—P. **Next row**—K1, (K2tog) 8 [9] times, K1 (10 [11] sts). **Next row**—P.

Break yarn, thread through remaining sts, draw up tightly and fasten off securely.

TO MAKE UP

Childs Play Double Knitting—Do not press.

Fairytale Double Knitting—Press as for Coat.

Join seam. Press seam on **Fairytale Double Knitting only**.

In C, make a pompon and sew to top of Hat.



We shall be happy to deal with your queries if you write to Sarah Bell, Patons & Baldwins Limited, Alloa, Scotland, enclosing a ball band of the yarn specified and a stamped addressed envelope.

PUBLISHED BY PATONS & BALDWIN'S LIMITED

Made and printed in Great Britain by Lund Humphries, Bradford and London

16776

CM
1
2
3
4
5
6
7
8
9
10
11
12
13
14
15
16
17
18
19
20
21
22
23